

Printing 3 Per Page 1099 Laser-All Forms

Printer / Driver	Workstation / Server	Device Code	Form	Top Margin	Notes
HP LJ 4 HP LJ 4P	Windows 95/ Windows NT	Device Config. Windows Printer Port	All	350	Last page will not print until another print job is sent to the printer
HP LJ 4P HP LJ 4	Windows 95/ Windows NT	Windows Printer	Misc Int	250	
HP LJ 4P HP LJ 4	Windows 95/ Windows NT	Windows Printer	Div	200	
HP LJ 5 HP LJ 4 Port	Windows 95/ Windows NT	Device Config. Windows Printer Port	Misc Int	350	Last page will not print until another print job is sent to the printer
HP LJ 5 HP LJ 4 Port	Windows 95/ Windows NT	Device Config. Windows Printer Port	Div	250	Last page will not print until another print job is sent to the printer
HP LJ 5 HP LJ 5P	Windows 95/ Windows NT	Windows Printer	Misc	250	
HP LJ 5 HP LJ 5P	Windows 95/ Windows NT	Windows Printer	Div Int	200	
HP LJ 1100 HP LJ 1100 Driver	Windows 95/ Windows NT	Windows Printer	Misc	275	
HP LJ 4000 HP LJ PCL5e Driver	Windows 95/ Windows NT	Windows Printer	Misc	275	
HP LJ 4000 HP LJ PCL5e Driver	Windows 95/ Windows NT	Windows Printer	Div Int	225	
HP LJ 4000 HP LJ 4P Driver	Windows 95/ Windows NT	Device Config. Windows Printer Port	Misc Int	350	Last page will not print until another print job is sent to the printer
HP LJ 4000 HP LJ 4P Driver	Windows 95/ Windows NT	Device Config. Windows Printer Port	Div	200	Last page will not print until another print job is sent to the printer
HP LJ 4050TN PS Series	Windows 95/ Windows NT	Windows Printer	Misc Int	275	
HP LJ 4050TN PS Series	Windows 95/ Windows NT	Windows Printer	Div	200	