

**MAS 90 and MAS 200  
W-2 Printing Guidelines**

O/S	FORM	PRINTER	DRIVER	TAB SETTING	TOP MARGIN	MISC NOTES
Windows 2000 Pro	Laser-2	HP 4000	HP 4000 PCL6	Default (1,4)	Default (350)	Retirement Plan Box Tab=52
Windows 2000 Pro	Laser-2	HP 1100A	HP 1100 (MS)	Default (1,4)	370	
Windows 2000 Pro	Laser-2	HP 4 plus	HP 4 plus	Default (1,4)	410	Retirement Plan Box Tab=52
Windows 2000 Pro	Laser-2	HP 4050TN	HP 4050 PCL6	Default (1,4)	370	
Windows 2000 Pro	Laser-4	HP 4000	HP 4000 PCL6	Tab Right=71 Skip=7	300	Retirement Plan Box Tab=52
Windows 2000 Pro	Laser-4	HP 1100A	HP 1100 (MS)	Tab Right=71 Skip=6	330	
Windows 2000 Pro	Laser-4	HP 4 plus	HP 4 plus	Tab Right=71 Skip=7	370	
Windows 2000 Pro	Laser-4	HP 4050TN	HP 4050 PCL6	Tab Right=71 Skip=7	Default (350)	Tab=1
Windows 2000 Pro	Single-Wide	Okidata ML 391 Turbo Epson Emulation	Okidata ML 391 Turbo	Tab To=3	220	Retirement Plan Tab=51
Windows 98	Laser-2	HP 4000	HP 4000 PCL6	Default (1,4)	Default (350)	Retirement Plan Box Tab=52
Windows 98	Laser-2	HP 1100A	HP 1100 (MS)	Default (1,4)	370	
Windows 98	Laser-2	HP 4 plus	HP 4 plus	(3,4)	Default (350)	Retirement Plan Box Tab=52
Windows 98	Laser-2	HP 4050TN	HP 4050 PCL6	Default (1,4)	370	
Windows 98	Laser-4	HP 4000	HP 4000 PCL6	Tab Right=71 Skip=7	300	Retirement Plan Box Tab=52
Windows 98	Laser-4	HP 1100A	HP 1100 (MS)	Tab Right=71 Skip=6	330	
Windows 98	Laser-4	HP 4 plus	HP 4 plus	Tab Right=71 Skip=7	370	
Windows 98	Laser-4	HP 4050TN	HP 4050 PCL6	Tab Right=71 Skip=7	Default (350)	Tab=1
Windows 98	Single-Wide	Okidata ML 391 Turbo Epson Emulation	Okidata ML 391 Turbo	Tab To=3	220	Retirement Plan Tab=51
Windows XP	Laser-2	HP 4000	HP 4000 PCL6	Default (1,4)	Default (350)	Retirement Plan Box Tab=52
Windows XP	Laser-2	HP 1100A	HP 1100 (MS)	Default (1,4)	370	
Windows XP	Laser-2	HP 4 plus	HP 4 plus	Default (1,4)	410	Retirement Plan Box Tab=52
Windows XP	Laser-2	HP 4050TN	HP 4050 PCL6	(2,4)	370	
Windows XP	Laser-4	HP 4000	HP 4000 PCL6	Tab Right=71 Skip=7	300	Retirement Plan Box Tab=52
Windows XP	Laser-4	HP 1100A	HP 1100 (MS)	Tab Right=71 Skip=6	330	
Windows XP	Laser-4	HP 4 plus	HP 4 plus	Tab Right=71 Skip=7	370	
Windows XP	Laser-4	HP 4050TN	HP 4050 PCL6	Tab Right=71 Skip=7	Default (350)	Tab=1
Windows XP	Single-Wide	Okidata ML 391 Turbo Epson Emulation	Okidata ML 391 Turbo	Tab To=3	220	Retirement Plan Tab=51
Windows ME	Laser-2	HP 4000	HP 4000 PCL6	Default (1,4)	Default (350)	Retirement Plan Box Tab=52
Windows ME	Laser-2	HP 1100A	HP 1100 (MS)	Default (1,4)	370	
Windows ME	Laser-2	HP 4 plus	HP 4 plus	Default (1,4)	410	Retirement Plan Box Tab=52
Windows ME	Laser-2	HP 4050TN	HP 4050 PCL6	(2,4)	370	
Windows ME	Laser-4	HP 4000	HP 4000 PCL6	Tab Right=71 Skip=7	320	Retirement Plan Box Tab=52 Tab to 1

**MAS 90 and MAS 200  
W-2 Printing Guidelines**

O/S	FORM	PRINTER	DRIVER	TAB SETTING	TOP MARGIN	MISC NOTES
Windows ME	Laser-4	HP 1100A	HP 1100 (MS)	Tab Right=71 Skip=6	330	
Windows ME	Laser-4	HP 4 plus	HP 4 plus	Tab Right=71 Skip=7	370	
Windows ME	Laser-4	HP 4050TN	HP 4050 PCL6	Tab Right=71 Skip=7	Default (350)	Tab=1
Windows ME	Single-Wide	Okidata ML 391 Turbo Epson Emulation	Okidata ML 391 Turbo	Tab To=3	220	Retirement Plan Tab=51
Windows 95	Laser-2	HP 4000	HP 4000 PCL6	Default (1,4)	Default (350)	Retirement Plan Box Tab=52
Windows 95	Laser-2	HP 1100A	HP 1100 (MS)	Default (1,4)	370	
Windows 95	Laser-2	HP 4 plus	HP 4 plus	(3,4)	Default (350)	Retirement Plan Box Tab=52
Windows 95	Laser-2	HP 4050TN	HP 4050 PCL6	Default (1,4)	370	
Windows 95	Laser-4	HP 4000	HP 4000 PCL6	Tab Right=71 Skip=7	300	Retirement Plan Box Tab=52
Windows 95	Laser-4	HP 1100A	HP 1100 (MS)	Tab Right=71 Skip=6	330	
Windows 95	Laser-4	HP 4 plus	HP 4 plus	Tab Right=71 Skip=7	370	
Windows 95	Laser-4	HP 4050TN	HP 4050 PCL6	Tab Right=71 Skip=7	Default (350)	Tab=1
Windows 95	Single-Wide	Okidata ML 391 Turbo Epson Emulation	Okidata ML 391 Turbo	Tab To=3	220	Retirement Plan Tab=51